Instruction Update of a multiuser system to version 2-4-8-2

Multiuser Server: 2-4-8-2

- 1. Log in to the V400 Multiuser Server and define your own password.
- 2. The V400 Multiuser Server can easily be found with the help of the "Revox Assistant" utility or an IP scanner.
- 3. If necessary, save the complete multiuser data record before the update by clicking the symbol in the main view ^T↓. The import / export menu field then appears. Assign a name in the adjacent text field and save your data with the button [Export all]. Export all ^{*} voxnet If only [Export] appears in the menu field, you are not in the main menu, but in a submenu. In this case, switch with the back arrow <i>the main level.
- 4. Navigate to the menu item System in the page list and click on "Install new version".

= REVOX	
ST Configurator	
🔲 Multiuser App	System Update
🖼 Terminal	Revox Multiuser version: 2.4.5.2 New version is available: 2.4.6.0
🖵 Monitor	Install new version Last successful check for update at 19.2.2021, 11:03:17
器 Network	Update Manually
■ System	Select setup file and update
La Account	
Logs	

Important instructions

App Update

In order to be able to use all new functions, we urgently advise you to bring the multiuser apps for iOS (\geq V2.5.0) and Android (\geq V2.4.8) up to date. You can get the apps free of charge from the Google Play Store or the Apple App Store.

REVOX

New in system 2-4-8-2 for V400 Multiuser Server

New Tidal login function (OAuth)

Tidal requires a new registration process. After the multiuser system update to version 2-4-8-2, every user with a Tidal subscription must log in again. During the new log in procedure, the Multiuser App redirects you to the Tidal page in order to complete the registration. After this registration, Tidal can be used under My Music as before.

New firmware for multiuser amplifiers

From mid-October 2021, the V219 (b) multiuser amplifiers will be factory equipped with a new PLL. If you equip or expand new or existing projects with V219 (b) multiuser amplifier, version 2-4-8-2 is required.

The volume slider in the web app is visible again if room status is anonymous

Bugfix for web app: if a room is switched on in an anonymous state, the volume slider will be displayed again.

REVOX

Kontakt/ Contact

Deutschland / Germany Revox Deutschland GmbH Am Krebsgraben 15, D 78048 VS-Villingen tel +49 7721 8704 0, fax +49 7721 8704 29 info@revox.de www.revox.de

Schweiz / Switzerland Revox (Schweiz) AG Wehntalerstrasse 190, CH 8105 Regensdorf tel +41 44 871 66 11, fax +41 44 871 66 19 info@revox.ch www.revox.ch

Österreich / Austria Revox Handels GmbH Josef-Pirchl-Strasse 38, AT 6370 Kitzbühel tel +43 535 666 299, fax +43 535 666 299 4 info@revox.at www.revox.at

Irrtümer und technische Änderungen vorbehalten. E&OE



Copyright by Revox GmbH, Germany.