






Instruction Update of a multiuser system to version 2-5-1-1

Multiuser Server: 2-5-1-1

1. Log in to the V400 Multiuser Server and define your own password.
2. The V400 Multiuser Server can easily be found with the help of the "Revox Assistant" utility or an IP scanner.
3. If necessary, **save** the complete multiuser data record **before** the update by clicking the symbol in the main view . The import / export menu field then appears. Assign a name in the adjacent text field and save your data with the button [Export all].   If only [Export] appears in the menu field, you are not in the main menu, but in a submenu. In this case, switch with the back arrow  into the main level.
4. Navigate to the menu item System in the page list and click on "Install new version".



Important instructions

App Update

In order to be able to use all new functions, we urgently advise you to bring the multiuser apps for iOS (\geq V2.5.0) and Android (\geq V2.4.8) up to date. You can get the apps free of charge from the Google Play Store or the Apple App Store.

Release Notes for V400 Multiuser Server Version 2-5-1-1

Network compatibility with Multiuser System 3.0:

If you want to operate an existing Multiuser 2.x system with a Multiuser 3.0 server (e.g. M500/M300) in the same network, it is absolutely necessary to update the Multiuser 2.x system to version 2-5-1-1! The update of the system should take place before the first start-up of a M500/M300, otherwise the Multiuser 2.x system will crash.

Kontakt/ Contact

Deutschland / Germany
Revox Deutschland GmbH
Am Krebsgraben 15, D 78048 VS-Villingen
tel +49 7721 8704 0, fax +49 7721 8704 29
info@revox.de
www.revox.de

Schweiz / Switzerland
Revox (Schweiz) AG
Wehntalerstrasse 190, CH 8105 Regensdorf
tel +41 44 871 66 11, fax +41 44 871 66 19
info@revox.ch
www.revox.ch

Österreich / Austria
Revox Handels GmbH
Josef-Pirchl-Strasse 38, AT 6370 Kitzbühel
tel +43 535 666 299, fax +43 535 666 299 4
info@revox.at
www.revox.at

Irrtümer und technische Änderungen vorbehalten. E&OE

